

DONNING ROOM - DONNING

Prepare Airway Equipment - medications, ETT, blade (McGrath preferred), stylette, syringes

*****HAND HYGEINE*****

Put on **PURPLE** Gloves (1st layer)

PAPR

***** you do NOT need an N-95 under PAPR*****

- Turn on PAPR and set at Level 2
- Secure PAPR belt with machine in small of your back
- adjust clasp to center of belly in front; secure dangling strap end
- Connect PAPR hose to hood and click in place
- Place PAPR hood on head

Check gloves for tear/defects; replace if needed

Surgical Gown

- Put arms into gown sleeves
- Secure the Velcro at back of neck
- Use ties to secure gown in a slip knot at your side (easy pull release)

Put on **WHITE** Surgical Gloves (2nd layer)

Use Duct tape around sleeve cuffs with tabs

Yellow Gown

- Put arms into gown sleeves first with thumbs through thumb holes; pull gown up around chest
- Place head with PAPR hood through neck opening gently; be careful not to tear gown
- Tie gown behind your back

Put on **BLUE** Surgical Gloves (3rd layer)

Option of purple gloves or sterile gloves (longer sleeve) cover white cuff of gown;

*****HAND HYGEINE*****

ENTER ROOM

PATIENT ROOM – PROCEDURES & CARE

RSI, No Mask Ventilation, McGrath Videoscope preferred, confirm with US
Wipe down ACCM McGrath handle with Purple-top Sani Wipes;
Leave all disposable intubation materials behind in patient room
(BCU McGrath may remain in room; place in double ziplock bag)

PREPARING TO EXIT & BEGINNING DOFFING IN PATIENT ROOM

Visually inspect gown, gloves, hood

- Use Sani-wipes to remove any contaminating material – ONE WIPE, ONE SWIPE

*****HAND HYGEINE*****

Remove 3rd set of gloves (**BLUE**);

touch only the outside of first glove & only the inside of second glove

- Thumb to ceiling, remove the first glove by pinching the outer portion near thumb
- Touching only the outside of the glove, pull glove all the way off (do not snap)
- Dispose of glove in waste bin
- Take finger of doffed hand and slide underneath cuff of remaining outer glove; you may regrasp the INSIDE of the glove if necessary
- Dispose of glove in waste bin

*****HAND HYGEINE*****

Remove **Yellow Gown**

- With both hands, grasp at shoulders pulling away to break the neck tab
- Arms out and away from you
- One hand to opposite shoulder touching only the outside of the gown, grasp and pull sleeve down all the way off the arm; let go
- Opposite hand to other shoulder, touching only the outside, grasp and pull sleeve down all the way off arm and let go
- Grasp the INSIDE of the gown that has now fallen away from you at the waist without touching yourself and pull outward to break the tie
- Roll gown in on itself touching only the inside; dispose of gown in waste bin

*****HAND HYGEINE*****

Remove 2nd set of gloves (**WHITE**);

touch only the outside of first glove & only the inside of second glove

*****HAND HYGEINE*****

Remove Surgical Gown

- Release slip knot tie
- With both hands, grasp at shoulders (surgical gown ONLY; not yellow gown) pulling away to break the neck tab
- Arms out and away from you
- One hand to opposite shoulder touching only the outside of the gown, grasp and pull sleeve down all the way off the arm; let go
- Opposite hand to other shoulder, touching only the outside, grasp and pull sleeve down all the way off arm and let go
- Grasp the INSIDE of the gown and roll in on itself touching only the inside
- Dispose of gown in waste bin

*****HAND HYGEINE*****

***** At this point you should only have the PAPR and 1st set of gloves (& ACCM McGrath)**

DOFFING ROOM – DOFFING CONTINUED

Once down to just PAPR and 1st set of gloves,
Exit the Patient Room, set down McGrath

*****HAND HYGEINE*** (yes, again)**

Disconnect PAPR hose from hood

- Press clasp at end of hose to disconnect hose
- Let hose fall to your side

*****HAND HYGEINE*****

Remove PAPR hood

- Grasp PAPR hood on both sides at ear level
- Pull up and off, leaning forward at 45 degrees and let drop into designated PAPR bin
- **DO NOT TOUCH YOUR FACE**

*****HAND HYGEINE*****

Remove PAPR machine and belt

- Grasp PAPR machine behind you
- Release belt clip and gently bring PAPR around to your front
- Turn off PAPR
- Place PAPR in designated bin

*****HAND HYGEINE*****

Remove 1st set of gloves (**PURPLE**)

touch only the outside of first glove & only the inside of second glove

- Thumb to ceiling, remove the first glove by pinching the outer portion near thumb
- Touching only the outside of the glove, pull glove all the way off (do not snap)
- Dispose of glove in waste bin
- Take finger of doffed hand and slide underneath cuff of remaining outer glove; you may regrasp the INSIDE of the glove if necessary
- Dispose of glove in waste bin

*****HAND HYGEINE*****

Apply new clean gloves and use Purple-top Sani wipes to wipe down PAPR pack, McGrath, and inside/outside of PAPR hood

*****HAND HYGEINE*****

Remove gloves used to wipe down equipment

*****HAND HYGEINE*****

EXIT DOFFING ROOM with equipment
WASH HANDS WITH SOAP AND WATER